


How to Optimize for Screen Readers in Digioh

Last Modified on 06/24/2026 4:44 pm EDT

Screen readers are an important part of keeping the internet accessible. The **ADA Box Controls for Screen Readers V2** extension ensures that your Digioh Campaigns are set up correctly for screen reader compatibility, including appropriate ARIA labels, tab ordering, and roles. Once installed, the extension runs automatically on all Campaigns in your account.

Installing the Extension

1. Log in to your Digioh account.
2. Navigate to the **Extensions** section under your account name menu.



3. Find **ADA Box Controls for Screen Readers V2** in the Accessibility section and click **Install**.



4. Once installed, make sure to click **Publish to Your Site** for the extension to start running.

The extension will now run on all Campaigns in your account.

Disabling the Extension for a Specific Campaign

If there is a Campaign you want to opt out of the extension, you can disable it using campaign-level metadata.

1. Open the Campaign in the Campaign Editor.

2. Navigate to **Settings > Campaign Settings > Campaign metadata** .

3. Add the following metadata:

- **Metadata Key:** disable_screen_reader
- **Value:** true

The screenshot shows the 'Campaign Settings' interface. At the top, there are controls for 'BORDER STYLE' (set to 'solid'), 'COLOR' (a grey circle), 'WIDTH' (set to '0'), and 'RADIUS' (set to '0'). Below this is a 'Campaign Margins' section with a toggle switch. The 'Extra CSS Styles' section has a toggle switch and a text area containing 'overflow:visible;' with an example 'box-shadow: 10px 5px 5px black;'. The 'Campaign Metadata' section is highlighted with a green box; it has a toggle switch and a table with two columns: 'KEY' and 'VALUE'. The table contains one entry: 'disable_screen_reader' and 'true'. Below this is a 'Quiz Settings are Disabled' section with a toggle switch and a note: 'Want quiz related settings for this campaign? Just switch this on. Heads up: Campaign Settings will close.' At the bottom right, there are two buttons: 'Apply & Close' and 'Preview'.

KEY	VALUE
disable_screen_reader	true

4. Click **Save** and publish the Campaign.

Related Reading

- [Setting Up ADA Box Controls for Screen Readers V2 in Digioh](#) — advanced configuration including image alt text, focus trapping, and additional metadata controls.