

Digioh Form Editor Overview

Last Modified on 06/24/2026 5:00 pm EDT

What You'll Learn in This Article:

- Build and Set up your Campaign
- Customize layout, forms, buttons, text, images, and more.
- Define form actions, button clicks, and overall display settings

Steps/Pages

The Main Page is the first page that appears on your Campaign. After a form is submitted the user can then be brought to a Thank You page. You can also create multi-step pop-ups with Extra Pages.

Steps/Pages

+ Add

Main Page

⚙️ ▼

⋮ (EP1) Email Address

⚙️ ▼

⋮ (EP2) Mobile Phone

⚙️ ▼

⋮ Thank You Page

⚙️ ▼

Campaign Options

Here is where you can change the campaign style (Popup, Sidebar, Inline, Banner), the display mode, add extra CSS and more.

Settings
OFF
299276: Sale Promo

Campaign Options

Campaign Type

Popup

Display Mode

Default

Responsive

Edge to Edge

Full Screen

Responsive Mode: Lets you control how the container scales up to a maximum height and width. Edit Responsive settings on Steps/Pages.

Opening & Closing Animation

Position of Popup in Window

Screen Overlay Background

COLOR

USE GRADIENT

USE IMAGE

OFF

OFF

CLICK OUTSIDE POPUP TO CLOSE

OFF

Layout

The Layout tab on each page is where you edit the campaign's dimensions, border, and background.

Settings
OFF
299276: Sale Promo Exit Intent Popup
Not Published
View Validation
Save Draft
Preview
Save & Publish

Main Page

Layout
Form
Buttons
Text
Images
HTML

Page Name

RESPONSIVE MAX BOX SIZE

Absolute Pixel Values (recommended)

MAX WIDTH

max width in pixels

550

MAX HEIGHT

max height in pixels

680

Dimensions

WIDTH

width in pixels

550

HEIGHT

height in pixels

680

Page Border

BORDER STYLE

COLOR

WIDTH

RADIUS

solid

1

0

Desktop

Mobile

OUR ANNUAL SITE-WIDE SALE IS BACK AGAIN!

Make sure you enjoy 25% OFF

Sale ends midnight July 25th!

SHOP NOW

Form

Under the form tab, you can add fields, style the labels and inputs.

Main Page  

Layout **Form** Buttons Text Images HTML

Form Fields Labels **Inputs**

Input Basics


INPUT HEIGHT

15  55

INPUT SPACING

0  15

CHECKBOXES TOP MARGIN

pixels  0

Error Message Position 

Choose where error messages appear.

Ghost Text Color 

Placeholder text is the hint that disappears when you click a field, guiding how to enter information.


COLOR



Input Text Styles

FONT FAMILY COLOR SIZE LINE HEIGHT

DM Sans  16 0



Here are the sections in the Form tab:

- **Form:** Turn the form on/off using the Eye icon, choose the action that happens after the form is submitted.

Layout **Form** Buttons Text Images HTML

Form Fields Labels Inputs

Form  

AFTER FORM SUBMIT 

Show Thank You Page 

OVERRIDE CAMPAIGN INTEGRATIONS 

LOADING IMAGE 

FORM CSS 

Form Size **Form Position** 

WIDTH HEIGHT X Y CENTER

280  62  131  495  

- **Fields:** Add and edit fields from the dropdown. Create custom fields and set them to Textbox, Dropdowns, Checkboxes, Radio Buttons, etc.

- **Labels:** Show/hide labels that appear above or in front of your fields. When Labels are toggled on, you will see settings to style the look of them. *Note: Labels for Radio Buttons or Checkboxes have their own show/hide toggle within their field options.*

- **Inputs:** Control the height, spacing, font, border, and background of your form inputs.

Buttons

Add form submission buttons, download buttons, close buttons, and more in the Buttons tab.

Layout Form **Buttons** Text Images HTML

Button 1 – SUBMIT

Button 1

Button Basics

ENTER BUTTON TEXT

SUBMIT


BUTTON ACTION WHEN CLICKED

Redirect to URL

REDIRECT URL

REDIRECT TYPE

Redirect current page



Drag and drop or resize buttons using the editor. You can also change colors, or use an image as a button.

Button Styles

Save time designing your Campaign. Set up some Campaign level styles. [Set Up Now](#)

Default Hover Selected Hover+Selected

☐ Copy changes to all states

Text

FONT FAMILY: Lato

COLOR:

FONT SIZE: 16

LINE HEIGHT:

[+ Add Custom Font](#)

TEXT ALIGNMENT: ☒ Left ☐ Center ☐ Right ☐ Justify

FONT STYLE: ☐ Normal ☐ Italic ☐ Underline ☒ Bold

Border

BORDER STYLE: none

Background

COLOR: ☒

USE GRADIENT: ☐

USE IMAGE: ☐

Program buttons by setting the click action to:

- Submit Form
- Close Box
- Redirect to URL
- Do Nothing (so you can add custom JavaScript)


- Download File
- Open Another Box
- Show Thank You Page or Extra Pages*



If you choose to make a button show another page, it won't submit the form. To show the Thank You Page after a user submits the form, you must go to the Form tab, and set "After Form Submit" to "Show Thank You Page."


Text

Edit text, font family, size, alignment, and even add custom CSS. You can also upload your own [Custom Fonts](#).




Images

Use the Images tab to add images, then control their size and position.



HTML

Add custom HTML blocks to create a more customized elements within your campaign, such as embedding a video.



Important: HTML blocks are intended for visual and presentational elements only. Buttons that submit forms or navigate between pages, and form fields tied to integrations, must use Digioh's native Button and Form elements. Custom HTML buttons and input fields cannot be connected to these types of interactions.

Campaign Styles

Click the **Settings** button at the top of the page to access **Campaign Styles**. There, you can define the styles you want for your text and buttons. Once you're done, just click **Apply and Close** to save and exit.

Manage Campaign Styles

Customize your Campaign-level styles to fit your brand, then easily apply them in the editor. It's like having your own campaign stylist—minus the fancy prices!

Changes to your styles will automatically update in the editor.

Typography

Set up styles for headlines, subtext, disclaimer

Lato 36px

Headline




+ Add Text Style

Buttons & Links

Predefine a variety of button styles, like primary buttons, next, previous, button links and more. Then the styles will be available to apply to your buttons in the editor.

+ Add Button Style

And that's it! Now simply select any text or button you want to style, and the campaign style you previously set.



Learn more about Campaign Style [here](#).

Thank You Page

To display a Thank You Page, set your button or form to “Show Thank You Page.”

The Thank You Page has the same options as the Main Page. If you want to copy the style settings from the Main Page, go to Layout and choose “Main Page” from the “Duplicate Content From Another Page” Section, then hit the Apply button. Or just use your Campaign Styles.

Next, edit your text and turn off any forms or buttons not required for the Thank You Page.

⌵

Thank You Page

⚙️

⬆️

LayoutFormButtonsTextImagesHTML

Text 3 – Thanks!⌵

🗑️📄+

Text 3

👁️

Text Basics

ENTER TEXT

Thanks!

Text Styles

Save time designing your Campaign. Set up some Campaign-level styles.

Set Up Now

FONT FAMILY


Lato⌵

COLOR

38⌵

LINE HEIGHT

⌵



Save Draft and then preview to see how your campaign will look.

Save Draft

Preview ⬆️

Save & Publish ⌵

Preview on Blank Site

Preview Exit

Preview Click

Preview Hover

Preview Scroll

Preview Flow Diagram

If everything looks good, publish your campaign by clicking Save & Publish. For it to show live on your site, ensure it has **Conditions** setup to determine how and where it will display.